

Adding a new driver class takes a few steps:

- Add the class in the class enumeration
- Add a header describing the class
 - ◆ its request functions
 - ◆ a structure containing pointer to request functions
 - ◆ utility function prototypes (blocking request wrappers, ?) [1]
- Add reference to the class in the driver structure
- Add a directory for the class
- Add a C-file with utility functions [1]

[1]: This is only needed if the class has such utility functions.

In the examples, we'll call the new class `foobar`.

Adding the class in the device type enumeration

Edit `hexo/include/hexo/device.h`, you'll see a `enum device_class_e`. Add the new device type at the end.

```
device_class_lcd,  
device_class_gpio,  
device_class_i2c,  
+ device_class_foobar,  
};
```

Adding a header describing the class

Create a file in `driver/include/device/foobar.h`. It may contain

- Callback definitions,
- Request function prototypes,
- Global utility functions.

See `trunk/mutekh/driver/include/device/char.h` for sample file.

The `struct dev_class_foobar_s` is a structure holding all the class-specific request functions. You may ensure this structure holds less pointers than the `DRV_MAX_FUNC_COUNT` constant defined in `trunk/mutekh/driver/include/device/driver.h`.

Don't forget to protect the new header against circular inclusions with the lines:

```
#ifndef __DEVICE_FOOBAR_H__  
#define __DEVICE_FOOBAR_H__  
  
#endif
```

We'll use that macro later.

Adding a reference to the class in the driver structure

Edit `trunk/mutekh/driver/include/device/driver.h` and add an entry in the `f` union of the `struct driver_s`.

You must protect it with the macros defined in the header of the class, in case the class is not included in legacy code.

Dont `#include` your driver class in `driver.h`.

```
#ifndef __DEVICE_FOOBAR_H__
    struct dev_class_foobar_s foobar;
#endif
```

Create a directory for the class

- create a `driver/device/foobar` directory,
- add a `Makefile` inside it,
- add `foobar` in the list of subdirectories in `driver/device/Makefile`.

Create the global helper functions file for your class

- create a `driver/device/foobar/device_foobar.c`,
- add it in `driver/device/foobar/Makefile`.